



環境設定シート

本書の構成

- A **ハードウェア構成シート**
本サーバにおけるハードウェアの構成を記録しておきます。
- B **BIOS セットアップユーティリティ設定シート**
本サーバにおけるBIOS セットアップユーティリティの設定値を記録しておきます。
- C **リモートマネジメントコントローラのWeb インターフェース設定シート**
リモートマネジメントコントローラにおけるWeb インターフェースの設定値を記録しておきます。
- D **障害連絡シート**
障害が発生した場合にサーバの状態を記入しておくシートです。

※デザインシート(Windows / Linux)は、「環境設定シート -ServerView Installation Manager編-」を参照してください。

■製品の呼び方

本文中の製品名称を、次のように略して表記します。

製品名称	本文中の表記
PRIMERGY TX2560 M2 / RX2560 M2	本サーバ、またはサーバ

■BIOS,iRMC S4ファームウェアについて

本書はBIOS版数 **R1.31.0以降**、iRMC S4 ファームウェア版数 **9.69F以降**、SDR版数 **3.22以降** に準拠して記述してあります。

■商標

記載されている会社名、製品名は各社の登録商標または商標です。
その他の各製品は、各社の著作物です。

A ハードウェア構成シート

本サーバにおけるハードウェアの構成を記録しておきます。
選択構成箇所については、選択した構成の()内に を付けておきます。

■3.5インチ内蔵オプション

搭載位置	搭載3.5インチ内蔵オプション
Bay1	
Bay2	
Bay3	
Bay4	
Bay5	
Bay6	
Bay7	
Bay8	
Bay9	
Bay10	
Bay11	
Bay12	

■2.5インチ内蔵オプション

搭載位置	搭載2.5インチ内蔵オプション
Bay1	
Bay2	
Bay3	
Bay4	
Bay5	
Bay6	
Bay7	
Bay8	
Bay9	
Bay10	
Bay11	
Bay12	
Bay13	
Bay14	
Bay15	
Bay16	
Bay17	
Bay18	
Bay19	
Bay20	
Bay21	
Bay22	
Bay23	
Bay24	
Bay25	
Bay26	
Bay27	
Bay28	
Bay29	
Bay30	
Bay31	
Bay32	

■RAMモジュール

搭載位置	搭載RAMモジュール
DIMM-1A	
DIMM-2A	
DIMM-3A	
DIMM-1B	
DIMM-2B	
DIMM-3B	
DIMM-1C	
DIMM-2C	
DIMM-3C	
DIMM-1D	
DIMM-2D	
DIMM-3D	
DIMM-1E	
DIMM-2E	
DIMM-3E	
DIMM-1F	
DIMM-2F	
DIMM-3F	
DIMM-1G	
DIMM-2G	
DIMM-3G	
DIMM-1H	
DIMM-2H	
DIMM-3H	

■CPU

搭載CPU	搭載位置	搭載位置
()	() CPU1	() CPU2
()	() CPU1	() CPU2

■PCIカード

拡張カード	PCIスロット位置											
	PCI-1	PCI-2	PCI-3	PCI-4	PCI-5	PCI-6	PCI-7	PCI-8	PCI-9	PCI-10	PCI-11	PCI-12
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()
	()	()	()	()	()	()	()	()	()	()	()	()

—: 搭載不可を示します。

B セットアップユーティリティ設定シート

本サーバにおけるBIOS セットアップユーティリティの設定値を記録しておきます。ご購入時の設定値から設定を変更していない場合は、「()ご購入時設定を変更していない」に \mathcal{L} を付けてください。設定を変更した場合は、「設定値」欄の()内に \mathcal{L} を付けてください。

BIOS セットアップユーティリティは以下の方法で起動します。
POST 中、画面に下記メッセージが表示されている間に、【F2】キーを押してください。
POST 終了後、BIOS セットアップユーティリティのMain メニューが表示されます。

<F2> BIOS Setup - <F12> Boot Menu

BIOS セットアップユーティリティを起動する前にシステムが起動してしまった場合は、
【Ctrl】+【Alt】+【Del】キーを押して、システムを再起動してください。

B.1 Mainメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
BIOS Information	American Megatrends	
BIOS Vendor	Fujitsu	
Customized by	x.x.x.x	
Core Version	UEFI 2.4; PI 1.3	
Compliance		
> System Information		■System情報確認画面へ
> Open Source Software License Information		
System Language	English	
System Date	xxx MM/DD/YYYY	現在の日付を表示／入力
System Time	HH:MM:SS	現在の時刻を表示／入力
Access Level	Administrator	

B.2 Advancedメニューの設定項目

設定項目	ご購入時設定	設定値
Advanced		
> Onboard Devices Configuration		■Onboard Devices Configurationサブメニューへ
> PCI Status		■PCI Statusサブメニューへ
> PCI Subsystem Settings		■PCI Subsystem Settingsサブメニューへ
> CPU Status		■CPU Statusサブメニューへ
> CPU Configuration		■CPU Configurationサブメニューへ
> Memory Status		■Memory Statusサブメニューへ
> Memory Configuration		■Memory Configurationサブメニューへ
> SATA Configuration		■SATA Configurationサブメニューへ
> CSM Configuration		■CSM Configurationサブメニューへ
> Trusted Computing *1		■Trusted Computingサブメニューへ
> USB Configuration		■USB Configurationサブメニューへ
> Super IO Configuration		■Super IO Configurationサブメニューへ
> Network Stack Configuration		■Network Stack Configurationサブメニューへ
> Option ROM Configuration		■Option ROM Configuration サブメニューへ
> VIOM		■VIOMサブメニューへ
> iSCSI Configuration		■iSCSI Configurationサブメニューへ

*1: 装置構成や環境により表示しない場合があります。

■Onboard Devices Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>Onboard Devices Configuration</u>		
Onboard CNA	Enabled	()Disabled ()Enabled
Onboard CNA Oprom *1	Enabled	()Disabled ()Enabled
CNA Standby	Enabled	()Enabled ()Disabled

*1 Onboard CNAがDisabledのときは非表示

■PCI Statusサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>PCI Status</u>		
PCI Slot 1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 2	Enabled	()Enabled ()Failed ()Empty
PCI Slot 3 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 4 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 5 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 6 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 7	Enabled	()Enabled ()Failed ()Empty
PCI Slot 8	Enabled	()Enabled ()Failed ()Empty
PCI Slot 9 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 10 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 11 *1	Enabled	()Enabled ()Failed ()Empty
PCI Slot 12 *1	Enabled	()Enabled ()Failed ()Empty

ご購入時の搭載状況により、設定値は変わります。搭載時の設定値はEnabledです。

*1 装置構成によっては非表示

■PCI Subsystem Settingsサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>PCI Subsystem Settings</u>		
ASPM Support	Disabled	()Disabled ()L1 Only
Above 4G Decoding	Disabled	()Disabled ()Enabled
DMI Control	GEN 2	()GEN 1 ()GEN 2
Memory Hole Size	2 GB	()2 GB ()3 GB
SR-IOV Support	Disabled	()Disabled ()Enabled

■CPU Statusサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>CPU Status</u>		
CPU 1	Enabled	()Enabled ()Failed
CPU 2 *1	Enabled	()Enabled ()Disabled ()Failed ()Empty

*1 ご購入時の搭載状況により、設定値は変わります。搭載時の設定値はEnabledです。

■CPU Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
CPU Configuration		
Hyper-Threading *7	Enabled	()Disabled ()Enabled
Active Processor Cores	0	搭載CPUのコア数を上限とする
Hardware Prefetcher	Enabled	()Enabled ()Disabled
Adjacent Cache Line Prefetch	Enabled	()Enabled ()Disabled
DCU Streamer Prefetcher	Enabled	()Enabled ()Disabled
DCU Ip Prefetcher	Enabled	()Enabled ()Disabled
Intel Virtualization Technology	Enabled	()Disabled ()Enabled
VT-d	Enabled	()Enabled ()Disabled
Intel TXT Support	Disabled	()Disabled ()Enabled
Power Technology	Energy Efficient	()Disabled ()Energy Efficient ()Custom
HWPM Support *1	Disabled	()Disabled ()HWPM NATIVE MODE ()HWPM OOB MODE
Enhanced SpeedStep *1*2	Enabled	()Disabled ()Enabled
Turbo Mode *1*2*3	Enabled	()Disabled ()Enabled
Override OS Energy Performance *1 *6	Disabled	()Disabled ()Enabled
Energy Performance *1*4	Balanced Performance	()Performance ()Balanced Performance ()Balanced Energy ()Energy Efficient
Utilization Profile *1*4	Even	()Even ()Unbalanced
CPU C1E Support *1	Enabled	()Disabled ()Enabled
Autonomous C-state Support *1	Disabled	()Disabled ()Enabled
CPU C3 Report *1*5	Disabled	()Disabled ()Enabled
CPU C6 Report *1*5	Enabled	()Disabled ()Enabled
Package C State limit *1	C6(Retention)	()C0 ()C2 ()C6 ()C6(Retention)
QPI L1	Enabled	()Disabled ()Enabled
QPI Link Frequency Select	Auto	()6.4 GT/s ()8.0 GT/s ()9.6 GT/s ()Auto
Uncore Frequency Override	Disabled	()Disabled ()Maximum ()Nominal
COD Enable	Auto	()Disabled ()Enabled ()Auto
Early Snoop	Auto	()Disabled ()Enabled ()Auto
Home Snoop Dir OSB	Auto	()Disabled ()Enabled ()Auto

*1 Power TechnologyがCustomのとき表示

*2 HWPM SupportがDisabledのとき表示

*3 Enhanced SpeedStepがEnabledのとき表示

*4 Overdrive OS Energy PerformanceがEnabledのとき選択可能

*5 Autonomous C-state SupportがDisabledのとき選択可能

*6 HWPM SupportがHWPM OOB MODEのとき非表示

*7 搭載CPUにより表示/非表示

■Memory Statusサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Memory Status		
DIMM-1A	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2A	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3A	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1B	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2B	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3B	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1C	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2C	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3C	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1D	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2D	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3D	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1E	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2E	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3E	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1F	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2F	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3F	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1G	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2G	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3G	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-1H	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-2H	Enabled	()Enabled ()Disabled ()Failed ()Empty
DIMM-3H	Enabled	()Enabled ()Disabled ()Failed ()Empty

ご購入時の搭載状況により、設定値は変わります。搭載時の設定値はEnabledです。

■Memory Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Memory Configuration		
Memory Mode	Normal	()Normal ()Mirroring ()Sparing
NUMA	Enabled	()Disabled ()Enabled
DDR Performance	Performance optimized	()Performance optimized ()Energy optimized
Patrol Scrub	Enabled	()Disabled ()Enabled

■SATA Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
SATA Configuration		
SATA Mode	AHCI Mode	()AHCI Mode ()RAID Mode
> SATA Controller Configuration		SATA Controller Configurationサブメニューへ
> sSATA Controller Configuration		sSATA Controller Configurationサブメニューへ
SATA Port 1 *1	状態を表示	表示のみ
SATA Port 2 *1	状態を表示	表示のみ
SATA Port 3 *1	状態を表示	表示のみ
SATA Port 4 *1	状態を表示	表示のみ
SATA Port 5 *1	状態を表示	表示のみ
SATA Port 6 *1	状態を表示	表示のみ
sSATA Port 7 *1	状態を表示	表示のみ
sSATA Port 8 *1	状態を表示	表示のみ
sSATA Port 9 *1	状態を表示	表示のみ
sSATA Port 10 *1	状態を表示	表示のみ

*1 SATA ModeがRAID Modeのとき非表示

■SATA Controller Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
SATA Controller Configuration		
SATA Controller	Enabled	()Disabled ()Enabled
SATA Mode*1	AHCI Mode	SATA Configurationで選択したSATA Modeが表示される

*1 SATA ControllerがEnabledのとき表示

■sSATA Controller Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
sSATA Controller Configuration		
sSATA Controller	Enabled	()Enabled ()Disabled
SATA Mode*1	AHCI Mode	SATA Configurationで選択したSATA Modeが表示される

*1 sSATA ControllerがDisabledのとき非表示

■CSM Configurationサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Compatibility Support Module Configuration		
Launch CSM	Enabled	()Disabled ()Enabled
Boot option filter *1	Legacy only	()UEFI and Legacy ()Legacy only ()UEFI only
Launch PXE OpROM Policy *1	Legacy only	()Do not launch ()UEFI only ()Legacy only
Launch Storage OpROM policy *1	Legacy only	()Do not launch ()UEFI only ()Legacy only
Other PCI device ROM priority *1	Legacy only	()UEFI only ()Legacy only

*1 Launch CSMがEnableのとき表示

■Trusted Computingサブメニュー

()ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Trusted Computing Settings		
TPM Support	Enabled	()Disabled ()Enabled
TPM State *1	Enabled	()Disabled ()Enabled
Pending TPM operation *1 *2	None	()None ()Enable Take Ownership
HashPolicy *3	SHA-1	()Disable Take Ownership ()TPM Clear
		()SHA-1 ()SHA-2
TPM 1.2 Device Found *1		*表示のみ(TPM1.2搭載時)
TPM 2.0 Device Found *1		*表示のみ(TPM2.0搭載時)
Current TPM Status Information *1		
TPM Enabled Status: *1	xxxxxxxxxx	現在の状態を表示
TPM Active Status: *1	xxxxxxxxxx	現在の状態を表示
TPM Owner Status: *1	xxxxxxxxxx	現在の状態を表示

装置構成や環境により表示が異なる場合があります。

*1 TPMモジュールを搭載し、TPM SupportがEnabledのとき表示

*3 TPM2.0搭載時のみ選択可能

*2 TPM StateがEnabledのとき選択可能

■USB Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
USB Configuration		
USB Devices: x Drives, x Keyboards, x Mice, x Hubs		
xHCI Mode *1	Auto	() Smart Auto () Auto () Enabled () Disabled
Legacy USB Support	Enabled	() Enabled () Disabled () Auto
Onboard USB Controllers	Enabled	() Enabled () Disabled
> USB Port Security		■ USB Port Securityサブメニューへ

*1 Onboard USB ControllersをDisabledに設定時、自動的にDisabledに切り替わります。

■USB Port Securityサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
USB Port Control	Enable all ports	() Enable all ports () Enable front and internal ports () Enable rear and internal ports () Enable internal ports only

■Super IO Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Super IO Configuration		
Super IO Chip	状態を表示	表示のみ
> Serial Port 1 Configuration		■ Serial Port 1 Configurationサブメニューへ

■Serial Port 1 Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Serial Port 1 Configuration		
Serial Port	Enabled	() Disabled () Enabled
Device Settings *1	IO=3F8h; IRQ=4;	表示のみ
Change Settings *1	Auto	() Auto () IO=3F8h; IRQ=4; () IO=3F8h; IRQ=3,4,5,6,7,9,10,11,12; () IO=2F8h; IRQ=3,4,5,6,7,9,10,11,12; () IO=3E8h; IRQ=3,4,5,6,7,9,10,11,12; () IO=2E8h; IRQ=3,4,5,6,7,9,10,11,12;

*1 Serial PortがEnabledのとき表示

■ Network Stack Configuration サブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>Network Stack Configuration</u>		
Network Stack	Disabled	()Disabled ()Enabled
Ipv4 PXE Support *1	Enabled	()Disabled ()Enabled
Ipv6 PXE Support *1	Enabled	()Disabled ()Enabled

*1 Network StackがEnabledのとき表示

■ Option ROM Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>Option ROM Configuration</u>		
Launch Slot 1 OpROM	Enabled	()Disabled ()Enabled
Launch Slot 2 OpROM	Enabled	()Disabled ()Enabled
Launch Slot 3 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 4 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 5 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 6 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 7 OpROM	Disabled	()Disabled ()Enabled
Launch Slot 8 OpROM	Disabled	()Disabled ()Enabled
Launch Slot 9 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 10 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 11 OpROM *1	Disabled	()Disabled ()Enabled
Launch Slot 12 OpROM *1	Disabled	()Disabled ()Enabled

ご購入時の搭載状況により、設定値は変わります。搭載時の設定値はEnabledです。

*1 装置構成によっては非表示

■ VIOMサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>VIOM</u>		
VIOM-flag	Disabled	表示のみ

■ iSCSI Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
<u>iSCSI Initiator Name</u>		
> Add an Attempt		[(4~233文字)]
> Delete Attempts		
> Change Attempt Order		

装置構成や環境により表示が異なる場合があります。

B.3 Securityメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Password Description Administrator Password User Password *1 Skip Password on WOL *2 FLASH Write User Password on Boot *2 > Secure Boot Configuration	 <div style="border: 1px dashed black; padding: 2px;">Disabled</div> <div style="border: 1px dashed black; padding: 2px;">Enabled</div> <div style="border: 1px dashed black; padding: 2px;">On Every Boot</div>	Administrator Password の新規設定 User Password の新規設定 () Disabled () Enabled () Disabled () Enabled () On every Boot () Disabled ■ Secure Boot Configurationサブメニューへ

*1 Administrator Passwordを設定後、設定可能

*2 User Passwordを設定後、設定可能

■ Secure Boot Configurationメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Secure Boot Configuration Platform Mode Secure Boot Vendor Keys Secure Boot control Secure Boot Mode > Key Management *1	状態を表示 状態を表示 状態を表示 <div style="border: 1px dashed black; padding: 2px;">Disabled</div> <div style="border: 1px dashed black; padding: 2px;">Standard</div>	Administrator Password の設定の有無を表示 () Disabled () Enabled () Standard () Custom ■ Key Managementサブメニューへ

*1 Secure Boot ModeのCustom設定時に設定可能

■ Key Managementメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Factory Default Key Provision Enroll all Factory Default keys *1 Delete all Secure Boot variables *2 Save all Secure Boot variables Platform Key Key Exchange Key Authorized Signatures Forbidden Signatures Authorized TimeStamps	<div style="border: 1px dashed black; padding: 2px;">Enabled</div> 状態を表示 状態を表示 状態を表示 状態を表示 状態を表示	() Disabled () Enabled () Set New Key () Delete Key () Set New Key () Append Key () Delete Key () Set New Key () Append Key () Delete Key () Set New Key () Append Key () Delete Key () Set New Key () Append Key

*1 Factory Default Key ProvisioningがEnabledのとき表示

*2 Factory Default Key ProvisioningがDisabledのとき表示

B. 4 Powerメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Power Settings		
Power-on Source	BIOS Controlled	() BIOS Controlled () ACPI Controlled
> Wake-Up Resources *1		■ Wake-Up Resourcesサブメニューへ

*1 Power-on SourceがBIOS Controlledのとき選択可能

■ Wake-Up Resourcesサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Wake-Up Resources		
LAN	Enabled	() Disabled () Enabled
Wake On LAN boot *1	Boot Sequence	() Boot Sequence () Force LAN Boot

*1 LANがEnabledのとき選択可能

B. 5 Server Mgmtメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Firmware Version	状態を表示	表示のみ
SDRR Version	状態を表示	表示のみ
Asset Tag	System Asset Tag	[]
BIOS Parameter Backup	Disabled	()Disabled ()Enabled
Onboard Video *1	Enabled	()Disabled ()Enabled
Boot Retry Counter	3	[] (0-7)
Power Cycle Delay	7	[]Seconds (0-15)
ASR&R Boot Delay	2	[]Minutes (1-30)
Temperature Monitoring	Disabled	()Disabled ()Enabled
Fan Control	Auto	()Auto ()Full
Event Log Full Mode	Overwrite	()Overwrite ()Maintain
Load iRMC Default Values	No	()No ()Yes
Power Failure Recovery	Previous State	()Always Off ()Previous State ()Always On
Serial Multiplexer	System	()System ()iRMC
Boot Watchdog	Disabled	()Enabled ()Disabled
Timeout Value *2	100	[]seconds (1-100)
Action *2	Continue	()Continue ()Reset ()Power Cycle
> iRMC LAN Parameters Configuration		■ iRMC LAN Parameters Configurationサブメニューへ
> Console Redirection		■ Console Redirectionサブメニューへ

*1 グラフィックスカード搭載時に設定可

*2 Boot watchdogがEnabledのとき設定可

■ iRMC LAN Parameters Configurationサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
iRMC LAN Parameters Configuration		
Management LAN	Enabled	()Disabled ()Enabled
iRMC MAC Address*1	状態を表示	
Management LAN Port *1	Management	()Management ()Shared
Management LAN Speed *1	Auto	()Auto ()100 Mbit/s Full Duplex ()100 Mbit/s Half Duplex ()10 Mbit/s Full Duplex ()10 Mbit/s Half Duplex ()1000 Mbit/s
Management VLAN *1	Disabled	()Enabled ()Disabled
VLAN ID *1*2	0	[] (0-4094)
VLAN Priority *1*2	0	[] (0-7)
iRMC IPv4 LAN Stack *1	Enabled	()Disabled ()Enabled
IP Configuration *1*3	use DHCP	()use DHCP ()use static configuration
IP Address *1*3	0.0.0.0	use static configurationを選択時、入力可能
Subnet Mask *1*3	0.0.0.0	use static configurationを選択時、入力可能
Gateway Address *1*3	0.0.0.0	use static configurationを選択時、入力可能
iRMC IPv6 LAN Stack *1*4	Enabled	()Disabled ()Enabled
Link Local Address *1*4*5	状態を表示	
- *1*4*5	状態を表示	

*1 Management LANがEnabledのとき表示

*2 Management VLANがEnabledのとき表示

*3 iRMC IPv4 LAN StackがEnabledのとき表示

*4 構成や環境によってIPv6のネットワーク情報が表示される場合があります

*5 iRMC IPv6 LAN StackがEnabledのとき表示

■ Console Redirectionサブメニュー

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Console Redirection		
Console Redirection:	Disabled	()Disabled ()Serial 1
Baud Rate: *1	9600	()9600 ()19.2K ()38.4K ()57.6K ()115.2K
Protocol: *1	VT100+	()VT100 ()PC ANSI ()VT100+ ()VT-UTF8
Flow Control: *1	None	()None ()CTS/RTS

*1 Console RedirectionがSerial 1のとき表示

B. 6 Bootメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Boot Configuration		
Bootup NumLock State	Off	<input type="checkbox"/> On <input type="checkbox"/> Off
Quiet Boot	Disabled	<input type="checkbox"/> Disabled <input type="checkbox"/> Enabled
Check controllers health status	Enabled	<input type="checkbox"/> Disabled <input type="checkbox"/> Enabled
Boot error handling	Continue	<input type="checkbox"/> Continue <input type="checkbox"/> Pause and wait for key
Keep Void Boot Options	Disabled	<input type="checkbox"/> Disabled <input type="checkbox"/> Enabled
New Boot Option Policy	Place First	<input type="checkbox"/> Default <input type="checkbox"/> Place First <input type="checkbox"/> Place Last
PXE Boot Option Retry	Disabled	<input type="checkbox"/> Disabled <input type="checkbox"/> Enabled
Boot Removable Media	Enabled	<input type="checkbox"/> Disabled <input type="checkbox"/> Enabled
Boot Option Priorities		
Boot Option #1		接続デバイスに依存
Boot Option #2		接続デバイスに依存
Boot Option #3		接続デバイスに依存
Boot Option #4		接続デバイスに依存

B.7 Save & Exitメニューの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Save Changes and Exit Discard Changes and Exit Save Changes and Reset Discard Changes and Reset		
Save Options Save Changes Discard Changes		
Restore Defaults Save as User Defaults Restore User Defaults		
Boot Override Boot Option #1 Boot Option #2 Boot Option #3 Boot Option #4		接続デバイスに依存 接続デバイスに依存 接続デバイスに依存 接続デバイスに依存

C リモートマネジメントコントローラの Web インターフェース設定シート

リモートマネジメントコントローラにおける、Web インターフェースの設定値を記録しておきます。
ご購入時の設定値から設定を変更していない場合は、「() ご購入時設定を変更していない」に を付けてください。

C.1 System Information の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
System Overview		システムの情報を表示
Asset Tag Configuration		
System Asset Tag	System Asset Tag	[]
Operating System Information		
System Name		[]
System Description	Server	[]
System O/S		[]
System IP		[]
System Location	- unknown -	[]
System Contact	- unknown -	[]
AIS Connect		
AIS Connect Management		
Enable AIS Connect *1	無効	()有効 ()無効
Enable Service Mode *2	無効	()有効 ()無効
Send Analysis Files Now *1 *2	無効	()有効 ()無効
AIS Connect Configuration		
Use Proxy	無効	()有効 ()無効
Country	NOT SELECTED	[]
AIS Connect Remote Session		
Allow Remote Sessions	有効	()有効 ()無効
Disconnect Remote Sessions	無効	()有効 ()無効
Force Poll	無効	()有効 ()無効
CPU Utilization History		
CPU Utilization History Options		
CPU History Period	1 hour	()1 hour ()12 hours ()1 day ()1 week ()2 weeks ()1 month ()1 year ()5 years
Enable CPU Monitoring	無効	()有効 ()無効

*1: 設定には声明書に同意が必要です。

*2: AIS Connect Disclaimerに同意すると選択可能になります。

C.2 BIOSの設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Backup/Restoration		BIOSバックアップ設定
Automatic BiosParameter Backup		
Enabled	無効	()有効 ()無効
Status	状態を表示	
Backup BIOS Single Parameters in ServerView@ WinSCU XML format		
Backup Filename	xxxxxxxx_VX.X.X_RXX.XX.XX_for_XXXXX-XXX_yyyymmdd.pre	[]
Restoration BIOS Single Parameters in ServerView@ WinSCU XML format		
Restoration File		[]
BIOS Update		BIOSアップデート設定
BIOS Update from File		
Update File		[]
BIOS TFTP Update Settings		
TFTP Server		[]
Update File	bios.upc	[]

C.3 iRMC S4 の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
iRMC S4 Information		iRMCの情報を表示
License Key		
KVM	状態を表示	
MEDIA	状態を表示	
eLCM *1	状態を表示	
Please enter any license key into the area below!		[]
Miscellaneous iRMC S4 Options		Web インターフェースのデフォルト表示設定
Default Language	English	()English ()Deutsch ()日本語
Temperature Units	Degree Celsius	()Degree Celsius ()Degree Fahrenheit
Color Schema	Style Guide Version 2.2	()Style Guide Version 1 ()Style Guide Version 2 ()Style Guide Version 2.2
Show Video Redirection (Java Web Start) in Navigation	有効	()有効 ()無効
Show 'Logout' in Navigation	有効	()有効 ()無効
Enable 'Automatic Apply'	無効	()有効 ()無効
iRMC S4 Time		
iRMC S4 Time Options		
Time Mode	System RTC	()System RTC ()NTP Server
RTC Mode *2	Localtime	()Localtime ()UTC (Universal Time Coordinated)
Time Zone Configuration *2		
Time Zone *4	Berlin	[]
NTP(Network Time Protocol) Configuration *3		
NTP Server 1	pool.ntp.org	[]
NTP Server 2	time.nist.gov	[]
Time Zone *4	Berlin	[]
Save Configuration		
Save iRMC S4 Firmware settings in ServerView® WinSCU XML format		
Include Network Settings	無効	()有効 ()無効
Include User Settings	無効	()有効 ()無効
Include License Information	無効	()有効 ()無効
All other Firmware settings	無効	()有効 ()無効
Import iRMC S4 Firmware settings in ServerView® WinSCU XML format from file		
Config File		()Uploadなし ()Uploadあり
Certificate Upload		
CA Certificate upload from file		
CA Certificate file		()Uploadなし ()Uploadあり
SSL Certificate and DSA/RSA private key upload from file		
SSL Private Key file		()Uploadなし ()Uploadあり
SSL Certificate file		()Uploadなし ()Uploadあり
SSL DSA/RSA certificate or DSA/RSA private key upload via copy & paste		ボックス内に入力
Generate Certificate		
Certificate Creation		
Common Name (CN)	DNS項目にて設定した値	[]
Organization (O)	iRMC S4	[]
Organization Unit (OU)		[]
Country (C)		[]
State or Province (ST)		[]
City or Locality (L)		[]
Email Address		[]
Valid From	証明書の有効開始日	表示のみ
Valid for (days)	730	[](1 - 3650)
Key Length (bits)	2048	()1024 ()2048 ()4096

*1: カスタムメイドでライフサイクルマネジメントライセンス & モジュール オプションを手配した場合、ライセンスを有効に設定して出荷します。

*2: [Time Mode] が [System RTC] の場合に表示されます。

*3: [Time Mode] が [NTP Server] の場合に表示されます。

*4: [Time Zone] の表示はインストールされたOS設定により、上記と異なる場合があります

C.3 iRMC S4 の設定項目 (続き)

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
iRMC S4 Update		
Firmware Image Information		
Firmware Selector:	Auto-Firmware Image with highest Firmware version	<input type="checkbox"/> Auto-Firmware Image with highest Firmware version <input type="checkbox"/> Low Firmware Image <input type="checkbox"/> High Firmware Image <input type="checkbox"/> Select Firmware Image with oldest Firmware version <input type="checkbox"/> Select most recently programmed Firmware <input type="checkbox"/> Select least recently programmed Firmware
iRMC S4 Firmware Update from File		
Flash Selector:	Auto - inactive Firmware	<input type="checkbox"/> Auto - inactive Firmware <input type="checkbox"/> Low Firmware Image <input type="checkbox"/> High Firmware Image
Update File:		[]
iRMC S4 TFTP Settings		
TFTP Server		[]
Update File:	rom.ima_enc	[]
Flash Selector:	Auto - inactive Firmware	<input type="checkbox"/> Auto - inactive Firmware <input type="checkbox"/> Low Firmware Image <input type="checkbox"/> High Firmware Image

C.4 Power Management の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Power On/Off		
Boot Options		
Error Halt Settings	BIOSの値が反映される	()Continue ()Halt on errors
Boot Device Selector	No Change	()No Change ()PXE/iSCSI ()Hard-drive ()CDROM/DVD ()Floppy ()BIOS Setup
Boot Type	PC compatible (legacy)	()PC compatible (legacy) ()Extensible Firmware Interface Boot (EFI)
Next Boot Only	無効	()有効 ()無効
Power Control		
Power On	無効	()有効 ()無効
Power Off	無効	()有効 ()無効
Immediate Reset	無効	()有効 ()無効
Pulse NMI	無効	()有効 ()無効
Power Cycle	無効	()有効 ()無効
Graceful Power Off (Shutdown)	無効	()有効 ()無効
Graceful Reset (Reboot)	無効	()有効 ()無効
Press Power Button	無効	()有効 ()無効
IPMI Fencing Power Off		
Enable emergency System Power off handling for Power Control	無効	()有効 ()無効
Power Options		
Power Restore Policy	BIOSの値が反映される	()Always Power off ()Always Power on ()Restore to powered state prior to power loss
Power On/Off Time		スケジュールOn/Off 時刻設定
Sunday	設定無し	On Time[] Off Time[]
Monday	設定無し	On Time[] Off Time[]
Tuesday	設定無し	On Time[] Off Time[]
Wednesday	設定無し	On Time[] Off Time[]
Thursday	設定無し	On Time[] Off Time[]
Friday	設定無し	On Time[] Off Time[]
Saturday	設定無し	On Time[] Off Time[]
Everyday	設定無し	hh:mm[] hh:mm[]
Minutes in advance	0	SNMP Trap[] SNMP Trap[]

C.5 Power Consumption の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Consumption Options		
Power Consumption Options		
Power Control Mode	O/S controlled	消費電力コントロール () O/S controlled () Minimum Power () Scheduled () Power Limit
Power Monitoring Units	Watt	() Watt () BTU/h
Enable Power Monitoring	有効	() 有効 () 無効
Power Limit Options		
Power Limit	0	[] Watt (108-846)
Target for Power Regulation	80	[] Percent (70-90)
Tolerance Time Before Action	5	[] Minutes (0-600)
Action Reaching Power Limit	Continue	() Continue () Graceful Power Off (Shutdown) () Immediate Power Off
Enable dynamic Power Control	有効	() 有効 () 無効
Scheduled Power Consumption Configuration		
※Power Control ModeがScheduledの場合のみ表示されます		
Sunday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Monday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Tuesday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Wednesday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Thursday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Friday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Saturday		
Time 1		[]
Mode 1	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Time 2		[]
Mode 2	O/S controlled	() O/S controlled () Minimum Power () Power Limit
Everyday		
hh:mm		[]
Mode 1		() O/S controlled () Minimum Power () Power Limit
hh:mm		[]
Mode 2		() O/S controlled () Minimum Power () Power Limit
Power History		
Power History Options		
Power Monitoring Units	Watt	() Watt () BTU/h
Power History Period	1 hour	() 1 hour () 12 hours () 1 day () 1 week () 2 weeks () 1 month () 1 year () 5 years
Enable Power Monitoring	有効	() 有効 () 無効

C.6 Sensors の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Fans		
Fan Test		
Fan Check Time	23:00	Fan Testの動作時刻設定 [] HH:MM
Disable FAN Test	無効	()無効 ()有効
System Fans *1		
1 FAN1 SYS	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
2 FAN2 SYS	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
3 FAN3 SYS	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
4 FAN4 SYS	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
5 FAN5 SYS	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
6 FAN PSU1	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
7 FAN PSU2	Fail Reaction:Continue Shutdown Delay:90	()Continue ()Shutdown and Power-off Delay[]Seconds (0 - 600)
Temperature *1		
Temperature Sensor Information (in °Celsius)		
1 Ambient	Continue	温度異常時の動作設定 ()Continue ()Shutdown and Power-off
2 Systemboard 1	Continue	()Continue ()Shutdown and Power-off
3 Systemboard 2	Continue	()Continue ()Shutdown and Power-off
4 CPU 1	Continue	()Continue ()Shutdown and Power-off
5 CPU 2	Continue	()Continue ()Shutdown and Power-off
6 MEM A	Continue	()Continue ()Shutdown and Power-off
7 MEM B	Continue	()Continue ()Shutdown and Power-off
8 MEM C	Continue	()Continue ()Shutdown and Power-off
9 MEM D	Continue	()Continue ()Shutdown and Power-off
10 MEM E	Continue	()Continue ()Shutdown and Power-off
11 MEM F	Continue	()Continue ()Shutdown and Power-off
12 MEM G	Continue	()Continue ()Shutdown and Power-off
13 MEM H	Continue	()Continue ()Shutdown and Power-off
14 PCH	Continue	()Continue ()Shutdown and Power-off
15 LOM	Continue	()Continue ()Shutdown and Power-off
16 PSU1 Inlet	Continue	()Continue ()Shutdown and Power-off
17 PSU2 Inlet	Continue	()Continue ()Shutdown and Power-off
18 PSU1	Continue	()Continue ()Shutdown and Power-off
19 PSU2	Continue	()Continue ()Shutdown and Power-off
20 BBU	Continue	()Continue ()Shutdown and Power-off
21 RAID Controller	Continue	()Continue ()Shutdown and Power-off
22 HDD	Continue	()Continue ()Shutdown and Power-off

*1 装置構成により、表示が相違する場合があります。

C.7 Event Log の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
IPMI SEL content		
System Event Log Content		System Event Log の表示
Display Critical	有効	()有効 ()無効
Display Major	有効	()有効 ()無効
Display Minor	無効	()有効 ()無効
Display Info	無効	()有効 ()無効
CSS only	無効	()有効 ()無効
Show Resolutions	無効	()有効 ()無効
Internal Event Log		
Internal Event Log Content		System Event Log の表示
Display Critical	有効	()有効 ()無効
Display Major	有効	()有効 ()無効
Display Minor	有効	()有効 ()無効
Display Info	有効	()有効 ()無効
SEL Configuration		
Default System Event Log display filtering		
Display Critical	有効	()有効 ()無効
Display Major	有効	()有効 ()無効
Display Minor	無効	()有効 ()無効
Display Info	無効	()有効 ()無効
CSS only	無効	()有効 ()無効
Show Resolutions	無効	()有効 ()無効
	Ring Buffer	()Ring Buffer ()Linear Buffer
Default Internal Eventlog display filtering		
Display Critical	有効	()有効 ()無効
Display Major	有効	()有効 ()無効
Display Minor	有効	()有効 ()無効
Display Info	有効	()有効 ()無効
	Ring Buffer	()Ring Buffer ()Linear Buffer
Helpdesk Information		
Helpdesk		[]
Add Service Notice		ボックス内に入力

C.7 Event Log の設定項目 (続き)

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Syslog Configuration		
Syslog forwarding options		
Event forwarding through Syslog Enabled	無効	()有効 ()無効
Syslog server addresses		
Syslog Server 1		
Server 1 Port	514	[]
Protocol	UDP	()TCP ()UDP
Type		
IEL	有効	()有効 ()無効
SEL	有効	()有効 ()無効
Syslog Server 2		
Server 2 Port	514	[]
Protocol	UDP	()TCP ()UDP
Type		
IEL	有効	()有効 ()無効
SEL	有効	()有効 ()無効
Syslog Server 3		
Server 3 Port	514	[]
Protocol	UDP	()TCP ()UDP
Type		
IEL	有効	()有効 ()無効
SEL	有効	()有効 ()無効
Syslog filtering options		
Filtering scope	Basic	()Basic ()Extended
Message severity *1		
Critical	有効	()有効 ()無効
Major	有効	()有効 ()無効
Minor	無効	()有効 ()無効
Informational	無効	()有効 ()無効
Fan Sensors *2	Critical	()None ()Critical ()Warning ()All
Temperature Sensors *2	Critical	()None ()Critical ()Warning ()All
Critical Hardware Errors *2	All	()None ()Critical ()Warning ()All
System Hang *2	Warning	()None ()Critical ()Warning ()All
POST Errors *2	All	()None ()Critical ()Warning ()All
Security *2	Critical	()None ()Critical ()Warning ()All
System Status *2	None	()None ()Critical ()Warning ()All
Disk Drivers & Controllers *2	Warning	()None ()Critical ()Warning ()All
Network Interface *2	Critical	()None ()Critical ()Warning ()All
Remote Management *2	Warning	()None ()Critical ()Warning ()All
System Power *2	Critical	()None ()Critical ()Warning ()All
Memory *2	Warning	()None ()Critical ()Warning ()All
Other *2	None	()None ()Critical ()Warning ()All

*1: Filtering scope が Basic のときに表示

*2: Filtering scope が Extended のときに表示

C. 8 Server Management の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
ASR&R Options		
ASR & R Boot Delay (1 - 30)	BIOSの値が反映される	[] Minutes
Retry counter Max (0 - 7)	3	[]
Retry counter (0 - Max)	BIOSの値が反映される	[]
BIOS Recovery Flash	Disabled	() Enabled () Disabled
Prevent Power On on Critical Temperature	Disabled	() Disabled () Enabled
Power Cycle Delay (7 - 15)	BIOSの値が反映される	[] Seconds
Watchdog Settings		
Bootのみ、BIOSの値が反映される ウォッチドッグ設定		
Software Watchdog		
Enabled	無効	() 有効 () 無効
Software Watchdog	Continue	() Continue () Reset () Power Cycle
after timeout delay (1 - 100)	5	[] Minutes
Boot Watchdog		
Enabled	無効	() 有効 () 無効
Boot Watchdog	Continue	() Continue () Reset () Power Cycle
after timeout delay (1 - 100)	100	[] Minutes
HP System Insight Manager (HP SIM)		
Integration Options		
HP SIM Integration Enabled	有効	() 有効 () 無効
System UUID Options		
Get System GUID Resopnse Format	IPMI Specification compatible	() IPMI Specification compatible () SMBIOS 2.6 Specification compatible

C.9 Network Settings の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Ethernet		
Network Interface Settings		
MAC Address	iRMCのMACアドレスが表示される	[: : : :]
LAN Speed	BIOSの値が反映される	() Auto Negotiation () 1000 Mbit/s () 100 Mbit/s Full Duplex () 100 Mbit/s Half Duplex () 10 Mbit/s Full Duplex () 10 Mbit/s Half Duplex
LAN Port	BIOSの値が反映される	() Management LAN () Shared LAN
Max. Transmission Unit (MTU)	1500	[] (1280 - 1500)
Bonding Enabled	無効	() 有効 () 無効
IPv4 Enabled	BIOSの値が反映される	() 有効 () 無効
IPv6 Enabled	BIOSの値が反映される	() 有効 () 無効
IPv4 configuration		
IP Address	BIOSの値が反映される	[. . .]
Subnet Mask	BIOSの値が反映される	[. . .]
Gateway	BIOSの値が反映される	[. . .]
DHCP Enabled	BIOSの値が反映される	() 有効 () 無効
IPv6 configuration *1		
Manual IPv6 configuration	無効	() 有効 () 無効
Interface Identifier Source *2	EUI-64 (based on MAC address)	() Part of specified static address () EUI-64 (based on MAC address)
IPv6 Static Address *2	2880::64	[: : : :]
Prefix Length *2	0	[] (8 - 128)
IPv6 Static Gateway *2	::	[: : : :]
Current Static Address *2	アドレスが表示される	[: : : : /]
Link Local Address	アドレスが表示される	[: : : : /]
VLAN configuration		
VLAN Enabled	無効	() 有効 () 無効
VLAN Id	0	[] (0 - 4094)
VLAN Priority	0	[] (0 - 7)
Ports and Services		
Ports and Network Services Settings		
Web based access		
Session timeout	300	[] Seconds (60 - 60000)
HTTP Port	80	[] (1 - 65535)
HTTPS Port	443	[] (1 - 65535)
Force HTTPS	無効	() 有効 () 無効
Enable TLS 1.1	有効	() 有効 () 無効
Enable TLS 1.2	有効	() 有効 () 無効
Enable Auto Refresh	有効	() 有効 () 無効
Refresh every	120	[] Seconds (10 - 60000)
Text based access		
Telnet Port	3172	[] (1 - 65535)
Session Drop Time	10	[] Minutes (0 - 120)
SSH Port	22	[] (1 - 65535)
Telnet Enabled	無効	() 有効 () 無効
SSH Enabled	有効	() 有効 () 無効
SSH authentication mode	login using password	() login using key () login using password
IPMI over LAN		
IPMI over LAN Enabled	有効	() 有効 () 無効
Redfish		
Redfish Service Enabled	有効	() 有効 () 無効

*1: IPv6 Enabledが有効時に表示されます。

*2: Manual IPv6 configurationが有効時に表示されます。

C.9 Network Settings の設定項目 (続き)

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Proxy Settings		
Proxy Settings		
Proxy Server		[]
Proxy Port	80	[]
Proxy User		[]
Password	*****	[] 表示は*となる
Confirm Password		[]
DNS		
DNS Settings		
DNS Enabled	有効	()有効 ()無効
Obtain DNS configuration from DHCP	無効	()有効 ()無効
DNS Domain		[]
DNS Search Path		[]
DNS Server 1		[]
DNS Server 2		[]
DNS Server 3		[]
DNS Retries	BIOSの値が反映される	[] (1-5)
DNS Timeout	5	[]Seconds (1-30)
DNS Name		
Register DNS Name	Register DHCP Address in DNS via DHCP Server	()None ()Register DHCP Address in DNS via DHCP Server ()Register full domain name (FQDN) via DHCP in DNS ()DNS Update Enabled
Use iRMC S4 name instead of server hostname	有効	()有効 ()無効
Add Serial Number	有効	()有効 ()無効
Add Extension	無効	()有効 ()無効
iRMC S4 Name	iRMC	[]
Extension	-iRMC	[]
DNS Name		状態を表示
SNMP		
SNMP Generic Configuration		
SNMP Enabled	無効	()有効 ()無効
SNMP Port	161	[](1 - 65535)
SNMP Protocol	All (SNMPv1/v2c/v3)	()All (SNMPv1/v2c/v3) ()SNMPv3 only
SNMPv1/v2c Community *1	public	[]
SNMPv1/v2c Permission *1	read only	状態を表示

*1: [SNMP Protocol] が [All (SNMPv1/v2c/v3)] の場合に表示されます。

C.10 Alerting の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
SNMP Traps		
SNMP Trap Destination		
SNMP Community	public	[]
SNMP User	NO SNMPV3 USER	表示のみ
engineID	状態を表示	[]
SNMP Server 1		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 2		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 3		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 4		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 5		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 6		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
SNMP Server 7		
IP Address or DNS Name		[]
Protocol	SNMPv1	()SNMPv1 ()SNMPv2c
Email		
Global Email Paging Configuration		
Email Alerting Enabled	無効	()有効 ()無効
SMTP Retries (0-7)	3	[]
SMTP Retry Delay (0-255)	30	[] Seconds
SMTP Response Timeout	45	[] Seconds
Primary SMTP Server Configuration		
SMTP Server	0.0.0.0	[]
SMTP Port	25	[] (1 - 65535)
Auth Type	None	()None ()SMTP AUTH(RFC2554)
Auth UserName *1		[]
Auth Password *1	*****	[] 表示は*となる
Confirm Password *1		[]
Send FQDN with EHLO/HELO	有効	()有効 ()無効
Secure (SSL)	無効	()有効 ()無効
Verify SSL Certificate	無効	()有効 ()無効
Secondary SMTP Server Configuration		
SMTP Server	0.0.0.0	[]
SMTP Port	25	[] (1 - 65535)
Auth Type	None	()None ()SMTP AUTH(RFC2554)
Auth UserName *1		[]
Auth Password *1	*****	[] 表示は*となる
Confirm Password *1		[]
Send FQDN with EHLO/HELO	有効	()有効 ()無効
Secure (SSL)	無効	()有効 ()無効
Verify SSL Certificate	無効	()有効 ()無効
Mail Format dependend Configuration		
From	MailFrom@domain.com	[]
Subject	FixedMailSubject	[]
Message	FixedMailMessage	[]
Admin. Name	ITS_UserInfo0	[]
Admin. Phone	ITS_UserInfo1	[]
Country Code		[]
Customer Id		[]
Server URL	http://www.server.com	[]
Attach Screenshot to 'Critical O/S Stop' event email	無効	()有効 ()無効

*1: Auth Type がSMTP AUTH(RFC 2554)の場合にのみ表示されます。

C.11 User Management の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
iRMC S4 User Information		
ID / Name	2 admin	2 []
	設定なし	3 []
	設定なし	4 []
	設定なし	5 []
	設定なし	6 []
	設定なし	7 []
	設定なし	8 []
	設定なし	9 []
	設定なし	10 []
	設定なし	11 []
	設定なし	12 []
	設定なし	13 []
	設定なし	14 []
	設定なし	15 []
	設定なし	16 []

[New User]で作成したUser Nameが表示されます。UserNameをクリックすると各UserName毎の設定項目画面が表示されます。
各ユーザ毎の設定項目画面は初期設定、または新規ユーザ作成時に設定した内容が表示されます。最大15ユーザまで設定出来ます。
(ユーザ1には設定できません)

■User "admin(2)" Configuration

ユーザID2のUserName設定画面です。

ユーザID2(admin)は、ご購入時に初期設定されているUserName/IDです。

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
iRMC S4 User - User 02 (User ID2)		
iRMC S4 User Information		
Name	admin	[]
Password	*****	[] 表示は*となる
Confirm Password		[]
Description	User 02 Description	[]
IPMI Configuration		
IPMI User Enabled	有効	()有効 ()無効
LAN Channel Privilege	OEM	()User ()Operator ()Administrator ()OEM
Serial Channel Privilege	OEM	()User ()Operator ()Administrator ()OEM
Configure User Accounts	有効	()有効 ()無効
Configure iRMC S4 Settings	有効	()有効 ()無効
Video Redirection Enabled	有効	()有効 ()無効
Remote Storage Enabled	有効	()有効 ()無効
Redfish Enabled	有効	()有効 ()無効
RedfishRole	Administrator	()ReadOnly ()Operator ()Administrator ()NoAccess
User Shell (Text Access)	Remote Manager	()Remote Manager ()None
SNMPv3 configuration		
SNMPv3 enabled *1	無効	()有効 ()無効
Access privilege	readonly	表示のみ
Authentication *1	SHA	()SHA ()MD5 ()None
Privacy *1	DES	()DES ()AES ()None
User SSHv2 public key upload from file (there is no key assigned to this user)		
Public Key file		[] ()Uploadなし ()Uploadあり
S/MIME certificate upload from file (there is no certifiacte assigned to this user)		
Certificate File		[] ()Uploadなし ()Uploadあり
Email Configuration		
Email Enabled	無効	()有効 ()無効
Encrypted	無効	()有効 ()無効
Mail Format	Standard	()Standard ()Fixed Subject ()ITS-Format ()SMS-Format
Prefered Mail Server	Automatic	()Automatic ()Primary ()Secondary
Email Address	User02@domain.com	[]
Use extra SMS Email Subject *2	無効	()有効 ()無効
SMS Email Subject *2		[]
Paging Severity Configuration		
Fan Sensors	Warning	()None ()Critical ()Warning ()All
Temperature Sensors	Warning	()None ()Critical ()Warning ()All
Critical Hardware Errors	All	()None ()Critical ()Warning ()All
System Hang	Critical	()None ()Critical ()Warning ()All
POST Errors	All	()None ()Critical ()Warning ()All
Security	Warning	()None ()Critical ()Warning ()All
System Status	None	()None ()Critical ()Warning ()All
Disk Drivers & Controllers	Critical	()None ()Critical ()Warning ()All
Network Interface	Warning	()None ()Critical ()Warning ()All
Remote Management	Critical	()None ()Critical ()Warning ()All
System Power	Warning	()None ()Critical ()Warning ()All
Memory	Critical	()None ()Critical ()Warning ()All
Other	None	()None ()Critical ()Warning ()All

*1: [Network Settings] - [SNMP] - [SNMP Generic Configuration] - [SNMP Enabled] を有効にした場合に設定可能。

*2: [Mail Format] が [SMS-Format] の場合にのみ表示されます。

■ User " ()" Configuration

ユーザID3~16のUserName設定画面です。

ユーザID3~16は、ご購入時設定が同じ内容の設定項目です。新規ユーザを複数作成した場合は、コピーしてお使いください。

() 新規ユーザを作成していない

設定項目	ご購入時設定	設定値
New User Configuration (User ID 3~16)		
iRMC S4 User Information		
Name	新規ユーザ作成時の設定	[]
Password	新規ユーザ作成時の設定	[] 表示は*となる
Confirm Password		[]
User Description	NewUser Description	[]
IPMI Configuration		
IPMI User Enabled	有効	()有効 ()無効
LAN Channel Privilege	User	()User ()Operator ()Administrator ()OEM
Serial Channel Privilege	User	()User ()Operator ()Administrator ()OEM
Configure User Accounts	無効	()有効 ()無効
Configure iRMC S4 Settings	無効	()有効 ()無効
Video Redirection Enabled	無効	()有効 ()無効
Remote Storage Enabled	無効	()有効 ()無効
Redfish Enabled	無効	()有効 ()無効
RedfishRole	NoAccess	()ReadOnly ()Operator ()Administrator ()NoAccess
User Shell (Text Access)	Remote Manager	()Remote Manager ()None
SNMPv3 configuration		
SNMPv3 enabled *1	無効	()有効 ()無効
Access privilege	readonly	表示のみ
Authentication *1	SHA	()SHA ()MD5 ()None
Privacy *1	AES	()DES ()AES ()None
User SSHv2 public key upload from file (there is no key assigned to this user) *2		
Public Key file		[] ()Uploadなし ()Uploadあり
S/MIME certificate upload from file (there is no certificate assigned to this user) *2		
Certificate File		[] ()Uploadなし ()Uploadあり
Email Configuration *2		
Email Enabled	無効	()有効 ()無効
Encrypted	無効	()有効 ()無効
Mail Format	Standard	()Standard ()Fixed Subject ()ITS-Format ()SMS-Format
Preferred Mail Server	Automatic	()Automatic ()Primary ()Secondary
Email Address	NewUser@domain.com	[]
Use extra SMS Email Subject *3	無効	()有効 ()無効
SMS Email Subject *3		[]
Paging Severity Configuration		
Fan Sensors	Warning	()None ()Critical ()Warning ()All
Temperature Sensors	Warning	()None ()Critical ()Warning ()All
Critical Hardware Errors	All	()None ()Critical ()Warning ()All
System Hang	Critical	()None ()Critical ()Warning ()All
POST Errors	All	()None ()Critical ()Warning ()All
Security	Warning	()None ()Critical ()Warning ()All
System Status	None	()None ()Critical ()Warning ()All
Disk Drivers & Controllers	Critical	()None ()Critical ()Warning ()All
Network Interface	Warning	()None ()Critical ()Warning ()All
Remote Management	Critical	()None ()Critical ()Warning ()All
System Power	Warning	()None ()Critical ()Warning ()All
Memory	Critical	()None ()Critical ()Warning ()All
Others	None	()None ()Critical ()Warning ()All

*1: [Network Settings] - [SNMP] - [SNMP Generic Configuration] - [SNMP Enabled] を有効にした場合に設定可能。

*2: [New User]で作成時には、表示されません。

*3: Mail Format がSMS-Formatの場合にのみ表示されます。

C.11 User Management の設定項目 (続き)

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
LDAP Configuration		
Global Directory Service Configuration		
LDAP Enabled	無効	()有効 ()無効
LDAP SSL Enabled	無効	()有効 ()無効
Disable Local Login *1	無効	()有効 ()無効
Always use SSL Login *2	無効	()有効 ()無効
Directory Server Type	Active Directory	()Active Directory ()Novell eDirectory ()OpenLDAP ()OpenDS/OpenDJ/Apache DS
Authorization Type	ServerView LDAP Groups with Authorization Settings on LDAP Server	()ServerView LDAP Groups with Authorization Settings on LDAP Server ()Standard LDAP Groups with Authorization Settings on iRMC
Primary LDAP Server		
LDAP Server		[]
LDAP Port	389	[] (1-65535)
LDAP SSL Port	636	[] (1-65535)
Backup LDAP Server		
LDAP Server		[]
LDAP Port	389	[] (1-65535)
LDAP SSL Port	636	[] (1-65535)
【Active Directory】選択時		
Domain name	domain.com	[]
Base DN	DC=domain, DC=com	*表示のみ
Groups directory as sub-tree from base DN		[]
Department name	department	[]
【Novell eDirectory / OpenLDAP / OpenDS/OpenDJ/ApacheDS】選択時		
Department name	department	[]
Base DN		[]
Groups directory as sub-tree from base DN		[]
User Search context		[]
Directory Service Access Configuration		
【Active Directory】選択時		
LDAP Auth UserName		[]
LDAP Auth Password	*****	[] 表示は*となる
Confirm Password		[]
【Novell eDirectory / OpenLDAP / OpenDS/OpenDJ/ApacheDS】選択時		
LDAP Auth Password	*****	[] 表示は*となる
Confirm Password		[]
Principal User DN		[]
Append Base DN to Principal User DN	無効	()有効 ()無効
Bind DN		*表示のみ
Enhanced User Login	無効	()有効 ()無効
Directory Service Email Alert Configuration		
LDAP Email Alert Enable	無効	()有効 ()無効
LDAP Alert Table Refresh	0	[] Hours (0-225)

*1: 【注意】LDAPを有効としディレクトリサーバが使用できない状態で、本設定を有効に設定するとWebインターフェースにログインできなくなります。

Novell eDirectoryは未サポートです。

*2: 【注意】LDAPが無効の場合、RFC2617認証/ログインを無効にし、httpsログイン画面を強制的に表示します。

C.11 User Management の設定項目 (続き)

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
CAS Configuration		
CAS Generic Configuration		
CAS Enabled	無効	()有効 ()無効
Enable SSL/HTTPS	有効	()有効 ()無効
Verify SSL Certificate	無効	()有効 ()無効
Always Display Login Page	無効	()有効 ()無効
CAS Network Port	3170	[] (1 - 65535)
CAS Server		[]
CAS Login URL	/cas/login	[]
CAS Logout URL	/cas/logout	[]
CAS Validate URL	/cas/validate	[]
Assign permissions from	Local assigned permissions	()Local assigned permissions ()Permissions retrieved via LDAP *1
CAS User Privilege and Permissions *2		
Privilege Level	User	()User ()Operator ()Administrator ()OEM
Configure User Accounts	無効	()有効 ()無効
Configure iRMC S4 Settings	無効	()有効 ()無効
Video Redirection Enabled	無効	()有効 ()無効
Remote Storage Enabled	無効	()有効 ()無効

*1: LDAP有効時のみ選択可能。

*2: Assign permissions from でLocal assigned permissions選択時のみ表示されます。

C.12 Console Redirection の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
BIOS Text Console		
BIOS Console Redirection Options		
Console Redirection Enabled	BIOSの値が反映される	()有効 ()無効
Serial Port Baudrate	BIOSの値が反映される	()9600 ()19200 ()38400 ()57600 ()115200
Serial Port Flow Control	BIOSの値が反映される	()None ()CTS/RTS(Hardware)
Terminal Emulation	BIOSの値が反映される	()VT100 ()PC-ANSI ()VT100+ ()VT-UTF8
Serial 1 Multiplexer	BIOSの値が反映される	()System ()iRMC S4
Video Redirection		
Video Redirection Options		
HTML5 Viewer Enabled	無効	()有効 ()無効
Default Mouse Mode	Absolute Mouse Mode	()Relative Mouse Mode ()Absolute Mouse Mode ()Other Mouse Mode
Local Monitor Off Control	Enabled	()Disabled ()Enabled ()Automatic Off when AVR is started
Oracle Java Deployment Ruleset	無効	()有効 ()無効
AVR Title	%USER%@%BMC_NAME%	
Current AVR Title		表示のみ

C.13 Virtual Media の設定項目

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
Remote Image Mount *1		
Remote CD/DVD Image Options		
Share Type	CIFS/SMB Common Internet File System	<input type="checkbox"/> HTTP Web Server <input type="checkbox"/> CIFS/SMB Common Internet File System <input type="checkbox"/> NFS Network File System
Server		[]
Share Name		[]
Image Name		[]
User Name		[]
Password	*****	[] 表示は*となる
Confirm Password		[]
Domain		[]
Remote Hard Disk Image Options *2		
Share Type	CIFS/SMB Common Internet File System	<input type="checkbox"/> HTTP Web Server <input type="checkbox"/> CIFS/SMB Common Internet File System <input type="checkbox"/> NFS Network File System
Server		[]
Share Name		[]
Image Name		[]
User Name		[]
Password	*****	[] 表示は*となる
Confirm Password		[]
Domain		[]
Media Option		
Virtual Media Options		
USB Attach Mode	Auto Attach	<input type="checkbox"/> Always Attach <input type="checkbox"/> Auto Attach
Number of CD/DVD Devices	2	[] (0-4)
Number of Harddisk Devices	0	[] (0-4)
Enable Remote Image Mount	有効	<input type="checkbox"/> 有効 <input type="checkbox"/> 無効

*1: Enable Remote Image Mount が無効の場合、非表示。

*2: Number of Harddisk Devices が 0 の場合、非表示。

C.14 Lifecycle Management の設定項目 *1

() ご購入時設定を変更していない

設定項目	ご購入時設定	設定値
CA Certificates		
CA Certificates update from file		[]
CA Certificates file:		()Uploadなし ()Uploadあり
CA Certificates update from text		ボックス内に入力 ()Uploadなし ()Uploadあり
Updates		
Update Settings		
Repository Location	https://support.ts.fujitsu.com	[]
Use Proxy	無効	()有効 ()無効
Skip VMware HCL verification	無効	()有効 ()無効
Offline Update		
Include BIOS and iRMC Firmware Updates	有効	()有効 ()無効
Default boot mode	PC compatible(legacy)	()PC compatible(legacy) ()Extensible Firmware Interface Boot(EFI)
Online Update		
Execution mode	Check for update	()Check for update ()Check for update and execute
Scheduling type	immediate	()immediate ()daily ()weekly ()monthly ()yearly ()once only
Offline Update		
Execution mode	Check for update	()Check for update ()Check for update and execute
Scheduling type	immediate	()immediate ()daily ()weekly ()monthly ()yearly ()once only
Custom Image		
Custom Image Download		
Execution mode	Download	()Download ()Download and execute
Scheduling type	immediate	()immediate ()once only
Custom Image URL		[]
Image Description		[]
Use Proxy	無効	()有効 ()無効
Intended boot mode	PC compatible(legacy)	()PC compatible(legacy) ()Extensible Firmware interface Boot(EFI) ()Dual Boot(legacy & EFI)
Deployment		
Deployment Update Settings		
Repository Location	https://webdownload.ts.fujitsu.com	[]
Use Proxy	無効	()有効 ()無効
Start Deployment Process		
Default boot mode	PC compatible(legacy)	()PC compatible(legacy) ()Extensible Firmware interface Boot(EFI) ()Dual Boot(legacy & EFI)
Profile File		[]
Scheduling type	immediate	()immediate ()daily ()weekly ()monthly ()yearly ()once only

*1: eLCMライセンスおよびmicroSDカードをインストールしている場合に表示します。

PRIMERGY TX2560 M2 / RX2560 M2

**環境設定シート
CA92344-1107-17**

**発行日 2022年12月
発行責任 富士通株式会社**

- 本書の内容は、改善のため事前連絡なしに変更することがあります。
- 本書に記載されたデータの使用に起因する、第三者の特許権およびその他の権利の侵害については、当社はその責を負いません。
- 無断転載を禁じます。